






```
1  uchar code table4[]=" Set Real Time ";
2  uchar code table5[]=" Set Open Time ";
3  uchar code table6[]=" Start Time: ";
4  uchar code table7[]=" 00:00:00 ";
5  uchar code table8[]=" End Time: ";
6  uchar code table9[]="Date: 2000/00/00";
7  uchar code table0[]="Time: 00:00:00 0";
8
9  bit Adjust;          //调节标志位, =1表示进入调节模式, =0是正常模式
10 bit Auto_flg;        //自动模式标志位, =1表示手动模式, =0是自动模式
11 sbit rs=P1^0;        //LCD1602
12 sbit rw=P1^1;        //LCD1602
13 sbit e=P1^2;         //LCD1602
14 sbit sck=P2^5;       //时钟端口
15 sbit io=P2^6;        //时钟端口
16 sbit rst=P2^7;       //时钟端口
17 sbit SELT =P1^6;     //选择键
18 sbit ENTER=P1^7;     //确认键
19 sbit UP =P3^0;       //加键
20 sbit DOWN =P3^1;     //减键
21 sbit MODE =P3^2;     //切换按键接口
22 sbit SWITCH=P3^3;    //手动开关
23 sbit AUTO_LED=P1^3;  //自动模式灯接口
24 sbit HAND_LED=P1^4;  //手动灯接口
25 sbit LAMP1=P3^4;     //灯接口
26 sbit LAMP2=P3^5;     //灯接口
27 sbit LAMP3=P3^6;     //灯接口
28 sbit LAMP4=P3^7;     //灯接口
29 sbit LIGHT1=P2^0;    //光线检测端口
30 sbit IN1=P2^2;
31 sbit OUT1=P2^1;
32 sbit DQ=P1^5;        //温度数据口
33 uchar Select_num;    //选择按键按下次数
34 uchar Enter_num;     //确认按键按下次数
35 uchar Switch_num;    //手动开关按键按下次数
36 float Year,Month,Day,Hour,Minute,Second; //时间设置值
37 uchar Week;
38 float Hour_H,Minute_H,Second_H; //设置开始时间
39 float Hour_L,Minute_L,Second_L; //设置结束时间
40 int Value1;          //人数
41 uchar IN1_flg=0;
42 uchar OUT1_flg=0;
43 uint Count;          //T0定时器中断计数次数
44 uchar Miao;
```